

Visionary GenICam


The Visionary-T CX/AG/DT, Visionary-S CX, Visionary-T Mini CX GenICam adapters follow the GenICam SFNC 2.3.

Requirements


The image acquisition driver requires a GenICam enabled development environment. To use the GenICam adapter the environment variable `GENICAM_GENTL64_PATH` must be set. Copy the `SICKVisionary<T/S/Tmini>TL_<X.Y.Z>.cti` file for your platform to the specified path.

QUICKSTART MVTec HALCON


1. Set the `GENICAM_GENTL64_PATH` environment variable to the folder path of the stored *.cti files.
2. Open a new Image Acquisition Assistant.




3. Press `Auto-detect Interfaces`, which should result in `GenICamTL`.



4. Go to `Connection` tab and press `Detect` to find devices.



5. **Connect** with device and switch to **Parameters** tab. To see all Parameters change the Visibility level.



For more information about the MVTec GenICam interface see:

<https://www.mvtec.com/products/interfaces/documentation/view/181114-standard-1811-progress-mvtecdoc-genicamtl>

For questions contact: TechSupport0905@sick.de